




How to make a reference plane on a cylinder in solidworks?

Description

Starting with this article which is the answer to your question How to make a reference plane on a cylinder in solidworks?.CAD-Elearning.com has what you want as free Solidworks tutorials, yes, you can learn Solidworks software faster and more efficiently here.

Millions of engineers and designers in tens of thousands of companies use Solidworks. It is one of the most widely used design and engineering programs and is used by many different professions and companies around the world because of its wide range of features and excellent functionality.

And here is the answer to your How to make a reference plane on a cylinder in solidworks? question, read on.

Introduction

As many you asked, how do you create a reference plane in Solidworks? The most common type of **reference plane** is an offset plane. To create an offset plane, select the Reference Geometry drop down on the CommandManager and choose the **Plane** option. Once the option to create a plane is open, select a face or another plane and set a distance for the offset.

Considering this, how do you create a **reference** plane at an angle in Solidworks?

Correspondingly, how do you **make** a plane on the surface in **Solidworks**?

1. Click Plane (Reference Geometry toolbar) or Insert > Reference Geometry > **Plane** .
2. In the PropertyManager, select an entity for First **Reference** .
3. Select a Second **Reference** and Third Reference as necessary to define the **plane**.
4. Click .

Subsequently, how do you create an axis reference in **SOLIDWORKS**?

1. Click Axis. on the Reference Geometry toolbar, or click Insert > Reference Geometry > Axis.
2. Select the axis type in the Axis PropertyManager, then select the required entities for that type.
3. Verify that the items listed in Reference Entities.
4. Click.
5. Click View > Hide/Show > Axes to see the new axis.

How do you reference geometry in SOLIDWORKS?

Left click insert 'Reference Geometry' to insert planes, axis, coordinate system, mate references, and points. Reference Geometry can also be found on the features toolbar. Left click on the pull down arrow and then left click on the desired tool.

How do you insert a reference plane?

1. On the Draw panel, click (Pick Lines).
2. On the Options bar, specify an offset, if desired.
3. Select the Lock option to lock the reference plane to the line.
4. Move the cursor near the line to which you want to place the reference plane and click.

How do you make a reference plane?

1. On the ribbon, click (Reference Plane). Architecture tab Work Plane panel (Reference Plane)
Structure tab Work Plane panel (Reference Plane)
2. To draw a line: On the Draw panel, click (Line).
3. To pick an existing line: On the Draw panel, click (Pick Lines).

How do you add an auxiliary plane in SOLIDWORKS?

1. Click Auxiliary View. (Drawing toolbar), or click Insert > Drawing View > Auxiliary.
2. Select a reference edge (not a horizontal or vertical edge, which would create a standard Projection View).
3. Move the pointer until the view is where you want, then click to place the view.

How do you make an angled plane on shape?

How do you make a 30 degree plane in Solidworks?

How do you create a sketch plane in Solidworks?

1. Click Plane (Sketch toolbar) or Tools > Sketch Entities > Plane to display the Sketch Plane PropertyManager.
2. From the FeatureManager design tree, select a plane, and click 3D Sketch on Plane (Sketch toolbar) or Insert > 3D Sketch on Plane.

How do you move a sketch to another plane in SOLIDWORKS?

1. Select the sketch in the FeatureManager design tree, and click Edit, Sketch Plane. “ or “
2. Select a new plane in the FeatureManager design tree or select a new planar face in the model for Sketch Plane/Face .
3. Click OK .

How do you change planes in SOLIDWORKS?

To change the plane, right click on the sketch in the Feature Manager and select the Edit Sketch Plane Icon. When you do, the Edit Sketch Plane command opens. To change the plane, right click in the window and clear the selections.

What is plane as a reference geometry Solidworks?

Reference geometry defines the shape or form of a surface or a solid. Reference geometry includes items such as planes, axes, coordinate systems, and points. You can use reference geometry in the creation of several kinds of features. For example: Planes are used in lofts and sweeps.

What is reference axis?

A reference axis is an axis that has only an input, such as position, pressure, or force. A reference axis does not have a Control Output and cannot control anything. A reference axis is commonly called a “half-axis”. Reference axes are typically used for monitoring some quantity, such as: Position.

What term is used when you need to create a new reference plane?

When you create the additional reference planes separately those reference planes are called global reference planes. Local Reference Planes: If you create the additional reference planes while creating the features itself, then the reference planes are called local reference planes.

How do you move a reference plane in Solidworks?

Move the plane by dragging the edge of the plane. Copy the plane by selecting a plane in the graphics area. Then hold down the Ctrl key and, using the edge, drag to a new location.

What is auxiliary plane?

Auxiliary Plane The plane which we draw to get the true shape of the inclined surface (often parallel to Principal Plane) is an auxiliary plane. Simply, the plane other than the Principal Plane (i.e. Horizontal Plane, Vertical Plane or Perpendicular Plane) is called Auxiliary Plane.

How do you draw an auxiliary projection?

To sketch an auxiliary view, you begin with orthographic. views of the object and add projection lines perpendicular (90°) to the slanted surface, adding a reference line any convenient distance from the view with the slanted surface.

Wrapping Up:

I believe you now know everything there is to know about How to make a reference plane on a cylinder in solidworks?. Please take the time to examine our CAD-Elearning.com site if you have any additional queries about Solidworks software. You will find a number of Solidworks tutorials. If not, please let me know in the comments section below or via the contact page.

The article makes the following points clear:

- How do you insert a reference plane?
- How do you add an auxiliary plane in SOLIDWORKS?
- How do you make an angled plane on shape?
- How do you make a 30 degree plane in Solidworks?
- How do you move a sketch to another plane in SOLIDWORKS?
- How do you change planes in SOLIDWORKS?
- What is plane as a reference geometry Solidworks?
- What is reference axis?
- What term is used when you need to create a new reference plane?
- How do you draw an auxiliary projection?